

SINEX_TRO - Solution (Software/Technique) INdependent EXchange Format for TROpospheric and meteorological parameters

Version 2.00 (April 2017)

R. Pacione, e-GEOS/ASI-CGS, Italy
J. Douša, GOP/RIGTC, Czech Republic

1. INTRODUCTION

This document describes the Solution (Software/Technique) Independent Exchange (SINEX) format for Tropospheric and meteorological parameters.

The effort to standardize the exchange format for tropospheric products has started in early 1997 by a number of IGS participants [Gendt, 1997]. In November 2010 [IGSMail-6298] SINEX_TRO format was slightly expanded to accommodate the addition of gradients. This expanded format has never been officially accepted and adopted. Due to the lack of the standardization, different software packages and organizations have started to use different field names referring to the same variables ad-hoc supporting optional and mandatory metadata, output files with different naming conventions and overall data contents. As a result, the format cannot be handled with a unique decoder.

According to further developments, new demands arose on the format for exchanging tropospheric parameters, in particular supporting:

- a) Parameters from different sources than space geodetic techniques such as numerical weather prediction models and re-analyses, radiosondes and water vapour radiometers,
- b) Long station names (9 characters) in concordance with RINEX 3 data format,
- c) Products including slant tropospheric delays,
- d) Parameters corresponding to long-term time series of individual stations.

This was the driver to develop a unique format to be adopted within all the IAG services and by all the techniques dealing with tropospheric parameters. However, because of difficulties in supporting all legacy and new features, it was decided to revise the format without keeping a full compatibility with any previous SINEX_TRO unofficial version. In this way new features, such as long station names or time series data support, could be introduced much easier while simplifying the format definition and usage.

Previously, the tropospheric products were provided in SINEX_TRO files [Gendt, 1997] along with the standard SINEX files using the corresponding filename. All common blocks (SITE/ID, SITE/ANTENNA, SITE/RECEIVER, SITE/ECCENTRICITY, SITE/COORDINATES etc.) could be then taken from the SINEX product. When tropospheric results were provided only in the SINEX_TRO format, a single file should contain mandatory all the metadata concerning the SITE specification.

Originally, the SINEX_TRO format was tightly linked to the SINEX developed by the IERS (<http://www.iers.org>). Because of difficulties of maintaining the SINEX_TRO format along with the SINEX and because of limitations in necessary developments (e.g. a support of long station names, variable length of data lines), the SINEX_TRO format V2.0 is decoupled from the SINEX while keeping a basic philosophy and a similar metadata format description. The most of metadata blocks thus became mandatory in the SINEX_TRO format in order to support a stand-alone and non-ambiguous metadata description in the same way for any file using the format.

2. PHILOSOPHY

The SINEX_TRO has as much as a simple and flexible design following the philosophy of the SINEX format (<http://www.iers.org/IERSEN/organization/AnalysisCoordinator/SinexFormat/sinex.html>) with regards to

metadata description and overall data structure. It is aimed at supporting site-specific and time series data stemming from various observing techniques or analyses, such as various space geodetic techniques (DORIS, GNSS, and VLBI), numerical weather prediction models, radiosondes, microwave radiometers, or others. All data and metadata refers to the time period or timestamp in order to support site-specific long-term data storage suitable for a time series analysis or climate research. Specific parameters, such as slant delays, are supported through the introduction of a new dedicated data block. The format supports all the necessary information for the conversion to the COST-716 format (http://egvap.dmi.dk/support/formats/egvap_cost_v22.pdf), so far widely used within GNSS-meteorology applications.

The format is able to accommodate data or products in the following scenarios:

- Parameters at a single site estimated, observed or interpolated in time,
- Parameters at a single site calculated from a vertical profile, using ray tracing or interpolating in space,
- Parameters for more sites coming from a unique source (analysis, method, provider etc.),
- Parameters from a combined solution including additional information from the combination process,
- Parameters from a long period including a full history of metadata,
- Parameters with a consistent temporal resolution (i.e. sampling rate) and representations (interpolation, modelling approach, etc.) while missing values are allowed when reported. Data representation and, optionally, interpolation should be described in the metadata section.

3. STRUCTURE

There is no limitation on the number of characters in data lines in SINEX_TRO. The SINEX_TRO file is subdivided into groups of data called blocks. A header and footer line encloses each block. The header and footer line are of 80 ASCII characters. Each block has a fixed format. The metadata blocks contain information on the file, the solution, its inputs and all the sites. Elements within each line are defined and separated by a blank character, at least.

A character field without information will have "-"s within its field and a missing numerical element will have an undefined value represented by number -999 (or using a column wise specific definition, see TROPO_PARAMETER_UNDEF and SLANTS_PARAMETER_UNDEF).

Important note: The undefined value should be **written/tested without the parameter scaling** (see TROPO_PARAMETER_UNITS and SLANT_PARAMETER_UNITS).

Okomentoval(a): [jd1]: This is still alternative solution if different values are needed for different parameters..... But hopefully simple constant -999 should work here.

Therefore, the SINEX_TRO file is readable in both forms "column-wise" and "line-wise". Character fields should be left-hand justified whenever applicable.

The first character of each line identifies the type of information that the line contains. Five characters are reserved. They have the following meaning when they are at the beginning of a line, they identify:

- '%' header and footer line,
- '*' comment line within the header and footer line,
- '+' title at the start of a block
- '-' title at the end of a block
- ' ' (empty space) data line within a block

No other character is allowed at the beginning of a line!

A SINEX_TRO file must start with a header line and end with a footer line.

The following blocks are defined:

FILE/REFERENCE (Mandatory)

INPUT/FILES	(Combined product only)
CENTERS/INFO_MODEL	(Combined product only)
CENTERS/INFO_SOLUTION	(Combined product only)
SITE/ID	(Mandatory)
SITE/RECEIVER	(Mandatory <u>for GNSS</u>)
SITE/ANTENNA	(Mandatory <u>for GNSS</u>)
SITE/COORDINATES	(Mandatory <u>for GNSS</u>)
SITE/ECCENTRICITY	(Mandatory <u>for GNSS</u> <u>Optional, if not provided, assumed NULL</u>)
SITE/GPS_ANTENNA -PHASE_CENTER	(Mandatory for GNSS)
TROP/DESCRIPTION	(Mandatory)
TROP/SOLUTION	(Mandatory <u>Mandatory for values in zenith directions</u>)
SLANT/SOLUTION	(<u>Optional</u> <u>Mandatory for values in slant directions</u>)

These block titles are immediately preceded by a "+" or a "-" as they mark the beginning or the end of a block. The block titles must be in capital letters. After a block has started (+) it must be ended (-) before another block can begin. The general structure is as follows:

```

%=TRO..... (Header line)-----|
.....|
+(BLOCK TITLE)-----|
.....|
.....|
-(BLOCK TITLE)-----|
.....|
+(BLOCK TITLE)-----|
.....|
.....|
-(BLOCK TITLE)-----|
.....|
%ENDTRO      (Footer line)-----|

```

Most fields within a SINEX_TRO line are separated by a single space or a sequence of spaces. In the following sections, each SINEX_TRO line is defined by its field name, a general description and format using FORTRAN notations.

A comment line (not to be confused with the FILE/COMMENT Block) can be written anywhere within the header and the footer line. All comment lines must start with a "*" in the first column. With the use of this character, information can be hidden from the software reading the file without deleting it from the file. A comment line format definition is provided in the Appendix 1.

4. DISSEMINATION

Three specific products are foreseen (and distinguished) in various dissemination scenarios supported by the SINEX_TRO format:

- 1) Individual analysis centre products,
- 2) Products from the combination centres,
- 3) Site-specific data time series.

4.1 File names

For file naming, it is recommended to use new format convention according to IGS products:

AAAVPPPTT_YYYYDDHHMM_LEN_SMP.TRO

or

AAAVPPPTT_YYYYDDHHMM_LEN_SMP_SITENAME.TRO

With:

- ‘_’ used as a separator between all the filename fields except the file extension,
- **AAA** (3-char) – analysis centre acronym,
- **V** (1-char) – *version / solution identifier*,
- **PPP** (3-char) – project/campaign identification: operational (OPS), demonstration (DEM), testing (TST), re-processing (REP), undefined ¹(UNK),
- **TTT** (3-char) – solution type: final (FIN), rapid (RAP), near real-time (NRT), real-time (RTM), sub-hourly (SUB), unknown (UNK)²,
- **YYYYDOYHHMM** (11-char) – string representing beginning time of nominal data interval. ‘0000000000’ can be used in case of a long time series storage,
- **LEN** (2-digits+1-char) – file frequency for specifying intended collection period of the file. Three characters are allowed for the format while the last character provides units minutes (xxM), hours (xxH), days (xxD), weeks (xxW), months (xxB), years (xxY), unspecified (00U). The last (00U) should be used if the file is used to store cumulative data,
- **SMP** (2-digits+1-char) – frequency for specifying data sampling rate. Three characters are allowed for the format with the last character providing the units: 100 Hertz (xxC), Hertz (xxZ), seconds (xxS), minutes (xxM), hours (xxH), days (xxD), weeks (xxW), months (xxB), years (xxY), unspecified (00U),
- **SITENAME** (4-char/9-char, optional) – site name consisting of variable length of 4 (old) or 9 (new) characters. New site conventional names according to the RINEX 3 convention are recommended. If a multi-station file is provided, the site name is omitted.

Examples:

```
GOPGOPSNRT_20150301000_01H_05M.TRO
GOP1DEMRTM_20150301000_05M_05M_GOPE.TRO
GOP2TSTSUB_20150301000_15H_05M_GOPE00CZE.TRO
GOP2OPSFIN_20150300000_01D_01H.TRO
ASI2REPFIN_20150301030_07D_01H.TRO
EUR2REPFIN_20150300030_07D_01H.TRO
```

For the file dissemination, GZIP (.gz) format is recommended. There is no recommendation for using upper or lower cases in filenames. Never mix lower case and upper case.

¹ The ‘undefined’ status should only be used when converting other format to this one where the status is not defined or obvious; newly generated files should always have a known and defined status.

² Solution type REP, FIN, RAP, NRT, RTM are related to the GNSS product type used in the processing. Generally REP, FIN, RAP are delivered on daily basis, NRT on hourly basis, while RTM in real time. SUB is similar to NRT but delivered on sub-hourly basis.

In case of a very large number of stations, it is recommended to deliver one SINEX_TRO file per station.

4.2 Analysis Centre Product

The Analysis Centres of the different IAG services submit, usually on daily or weekly basis, files containing estimated tropospheric parameters from specific site or network processed consistently. Only that information should be given which is directly related to the troposphere estimates. Additional data from other sources are allowed (similar like in time series outputs) until these are homogeneous and properly described in the header. These could be made available in support of information equivalent to the COST-716 format. The corresponding data blocks are:

FILE/REFERENCE	(Mandatory)
SITE/ID	(Mandatory)
SITE/RECEIVER	(Mandatory <u>for GNSS</u>)
SITE/ANTENNA	(Mandatory <u>for GNSS</u>)
SITE/COORDINATES	(Mandatory <u>for GNSS</u>)
SITE/ECCENTRICITY	(Optional, if not provided, assumed NULL Mandatory for GNSS)
ANTENNA-SITE/GPS <u>PHASE-PHASE_CENTER</u>	(Mandatory for GNSS)
TROP/DESCRIPTION	(Mandatory <u>for GNSS</u>)
TROP/SOLUTION	(Mandatory <u>for values in zenith directions</u>)
SLANT/SOLUTION	(Optional Mandatory for values in slant directions)

It is possible that a SINEX_TRO file contains data stemming from more sources, e.g. GNSS analysis completed with meteorological parameters observed in situ or derived from a numerical weather model. In such case, it should be however properly described in the file metadata sections.

4.3 Combination Product

It is necessary to define a combined product in case an IAG service, or any other service, delivers it for a single site or for a network. Besides blocks defined for the Analysis Centre products, the following blocks are added to support information from the combination process:

INPUT/FILES	(Mandatory)
CENTERS/INFO_MODEL	(Mandatory)
CENTERS/INFO_SOLUTION	(Mandatory)

4.4 Station Time Series

For the customer, who is interested in time series of tropospheric or other meteorological parameters for a specific location, it is convenient to have a product with separate files for each site.

The Station Time Series products aim at supporting application for which time series analysis is required (e.g. climate research, temporal modelling). A detailed description of a full history of metadata information has to be provided and is supported in the metadata definition since SINEX_TRO V2.0 can handle all metadata including site coordinates defined along with the time period specification.

5. TROPOSPHERIC MODELS AND OTHER RELATIONS

For the format definition, we need to define basic tropospheric models and other relations useful to exploit the format parameters.

5.1 Tropospheric models

The tropospheric path delay using the standard model and considering a symmetrical troposphere is expressed as follows:

$$d_{trop_symmetry} = m_h(E)ZHD + m_w(E)ZWD \quad (1)$$

where ZHD and ZWD are zenith hydrostatic and wet delays, E is the elevation angle, m_h and m_w are hydrostatic and wet mapping function.

The tropospheric path delay applying the extended model and considering the first-order asymmetry of the troposphere is defined as:

$$d_{trop_asymmetry} = m_h(E)ZHD + m_w(E)ZWD + m_g(E)[G_N \cos\phi + G_E \sin\phi] \quad (2)$$

with G_N and G_E horizontal tropospheric gradients in the North and East directions, ϕ azimuth angle, m_g gradient mapping function.

The zenith total delay (ZTD) is always defined as a sum of hydrostatic and wet delays in zenith (ZHD and ZWD), i.e. independently whether the troposphere asymmetry is modelled or not

$$ZTD = ZHD + ZWD \quad (3)$$

Total slant tropospheric delay (STD) is then defined as the delay along the signal path and includes residuals (res) to the extended model and excludes potential multipath and other systematic effects (mpt). It is expressed with the following relation:

$$STD = mf_h ZHD + mf_w ZWD + mf_g [G_N \cos\phi + G_E \sin\phi] + res - mpt \quad (4)$$

where mf_h , mf_w and mf_g are mapping factors necessary for an unambiguous reconstruction of all individual model parameters. The mapping factors are float numbers corresponding to the actual observation elevation angles, and they can be calculated from specified mapping function or using a method of meteorological model data ray-tracing.

It is common to consider an approximation that the dry (or hydrostatic) zenith path delay represents the a priori troposphere model in the analysis of data of space geodetic techniques while model parameters estimated in the adjustments corresponds roughly to the wet (non-hydrostatic part).

$$d_{trop_symmetry} = m_{approx}(E)ZTD_{apriori} + m_{estim}(E)\Delta ZTD_{estim} \quad (5)$$

5.2 Conversion between ZTD and IWV

The conversion of ZTD estimates to Integrated Water Vapour (IWV) is done in two steps.

Firstly, following the IERS Conventions (2010), ZHD can be estimated by means of the Saastamoinen (1972) model if the surface air pressure P_s is known. Then, ZHD is subtracted from ZTD to form ZWD:

$$ZWD = ZTD - ZHD \quad (6)$$

Secondly, ZWD is converted to IWV as:

$$IWV = \frac{10^6}{R_v \left(k_2' + \frac{k_3}{T_m} \right)} ZWD \quad (7)$$

where R_v is the specific gas constant of water vapour, k_2' [K/mb] and k_3 [K²/mb] are the refractivity coefficients (Bevis et al., 1994) and T_m is the weighted mean temperature of the atmosphere (Davis et al, 1985)

$$T_m = \frac{\int_H^\infty \frac{e}{T} dh}{\int_H^\infty \frac{e}{T^2} dh} \quad (8)$$

T_m can be either numerically integrated from the numerical weather model levels, or calculated from the analytical formula given by Askne and Nordius (1987).

5.3 Vertical parameter scaling

The temperature vertical scaling is usually approximated with the temperature lapse rate β [K/km]

$$T = T_0 - \beta(h - h_0) \quad (9)$$

where T and T_0 [K] are the temperature at height h and h_0 [m], respectively. Notice that the positive sign of the lapse rate is opposite to the U.S. Standard Atmosphere (1976). Similarly, the mean temperature vertical scaling is approximated with the mean temperature lapse rate β_m [K/km]

$$T_m = T_{m0} - \beta_m(h - h_0) \quad (10)$$

where T_m and T_{m0} [K] are the mean temperature at height h and h_0 [m].

The partial water vapour pressure vertical scaling is approximated using the parameter λ [-] and the formula introduced by Smith (1966) for a vertical approximation of the mixing ratio

$$e = e_0 \left(\frac{P}{P_0} \right)^{\lambda+1} = e_0 \left[1 - \frac{\beta(h - h_0)}{T_0} \right]^{\frac{(\lambda+1)g_m}{R_v\beta}} \quad (11)$$

where P , e and P_0 , e_0 [hPa] are the atmospheric pressure and partial water vapour pressure at geopotential height h and h_0 [km], respectively, and g_m is the standard gravitational acceleration 9.80665 [m.s⁻²] defined in the U.S. Standard Atmosphere (1976).

The zenith wet delay is approximated using the ZWD decay parameter and the formula introduced by Dousa and Elias (2014)

$$ZWD = ZWD_0 \left(\frac{P}{P_0} \right)^{\gamma+1} = ZWD_0 \left[1 - \frac{\beta(h - h_0)}{T_0} \right]^{\frac{(\gamma+1)g_m}{R_v\beta}} \quad (12)$$

where P , e and P_0 , e_0 [hPa] are the atmospheric pressure and partial water vapour pressure at geopotential height h and h_0 [km].

6. LIST OF PARAMETER TYPES

Parameter types are defined specifically for each SINEX_TRO data block.

6.1 Parameter types in zenith direction (TROP/SOLUTION)

Different tropospheric parameter types, according to the tropospheric models described in Section 5, are summarized in **Table 1**. Parameters can be provided as a product of 1) data analysis, e.g. from data of space geodetic technique, 2) data processing, e.g. from numerical weather model data fields, or radiosounding, or 3) direct observation method, e.g. from water vapour radiometer.

Table 1. Tropospheric parameter types in zenith direction

Acronyms	Description	Base unit ¹
TROTOT	tropospheric zenith total delay (ZTD)	m
TROWET	tropospheric zenith wet delay (ZWD)	m
TRODRY	tropospheric zenith dry/hydrostatic delay (ZHD)	m
TGNTOT	tropospheric total gradient – North component (wet + dry parts)	m
TGNWET	tropospheric dry gradient – North direction	m
TGNDRY	tropospheric wet gradient – North direction	m
TGETOT	tropospheric total gradient – East component (wet + dry parts)	m
TGEWET	tropospheric wet gradient – East component	m
TGEDRY	tropospheric dry gradient – East component	m
STDDEV	standard deviation for each estimated value reported in preceding column	
IWV	integrated water vapour	kg/m ²

¹Base unit is the reference unit for individual parameter scaling (see TROP/DESCRIPTION block).

Meteorological parameter types are summarized in **Table 2**. Parameters can be derived from 1) in situ observations, e.g. meteorological sensor, water vapour radiometer, or 2) data processing, e.g. from numerical weather model data fields or radiosounding.

Naformátováno: Písmo: Tučné

Table 2. Meteorological parameter types

Acronyms	Description	Base unit ¹
PRESS	atmospheric pressure	hPa
EPRESS	partial water vapour pressure	hPa
TEMDRY	dry temperature	K
HUMREL	relative humidity	%

¹Base unit is the reference unit for individual parameter scaling (see TROP/DESCRIPTION block).

Auxiliary parameter types in zenith direction including parameters for the vertical approximations are summarized in **Table 3**. These could provide 1) additional information about the product quality based on data analysis or, optionally, the differences in height to the reference position, e.g. for long-time series, to enable filtering of GNSS products etc. 2) necessary information for computing tropospheric ties needed for the comparisons at collocated stations.

Naformátováno: Písmo: Tučné

Table 3. Auxiliary parameter types in zenith direction including parameters for the vertical approximations

Acronyms	Description	Base unit ¹
ACOK	number of ACs taken into account for given epoch	-
ACDL	number of ACs deleted for given epoch	-
NSAT	number of satellites	-
GDOP	geometric dilution of precision	-
SCLHGT	pressure scale height	m
TEMLPS	temperature lapse rate	K/m
WVPDEC	water vapour pressure exponential decay	-
ZWDDEC	zenith wet delay exponential decay	-
WMTEMP	weighted mean temperature	K
WMTLPS	weighted mean temperature lapse rate	K/m

¹Base unit is the reference unit for individual parameter scaling (see TROP/DESCRIPTION block).

6.2 Parameter types in slant direction (SLANT/SOLUTION)

Slant tropospheric delay parameter types are supported since SINEX_TRO V2.0. The parameters are summarized in [Table 4](#). In addition, the following parameter of the TROP/SOLUTION block (see [Table 1](#)) TROWET, TROHYD, TGNTOT, TGETOT should be provided as well.

Naformátováno: Písmo: Tučné

Naformátováno: Písmo: (výchozí) Calibri, Tučné

Table 4. Tropospheric parameter types in slant directions

Acronyms	Description	Base unit ¹
SLTTOT	tropospheric slant total delay (STD)	m
SLTDRY	tropospheric slant dry delay (SHD), i.e. $mf_d * ZHD$	m
SLTWET	tropospheric slant wet delay (SWD), i.e. $mf_w * ZWD$	m
SLTGRD	tropospheric slant total delay due to the first-order horizontal gradient	m
SLTTGD	tropospheric slant dry delay due to the first-order horizontal gradient	m
SLTTGW	tropospheric slant wet delay due to the first-order horizontal gradient	m
STDDEV	standard deviation for the each estimated value reported in the column preceding	
SLTIWV	tropospheric slant integrated water vapour	kg/m ²

¹Base unit is the reference unit for individual parameter scaling (see TROP/DESCRIPTION block).

Auxiliary parameters for slant directions are supported in order to enable an optimal use of the slant parameters including a full reconstruction of any component of the tropospheric models defined in Section 5.

Table 5. Auxiliary parameter types in slant direction

Acronyms	Description	Base unit ¹
SAT	satellite code: Satellite System Satellite Number Satellite System: G=GPS R=GLONASS E=Galileo C=BeiDou	-
SAT__X	Satellite X-coordinate (Mandatory for Data Assimilation)	m

SAT__Y	Satellite Y-coordinate (Mandatory for Data Assimilation)	m
SAT__Z	Satellite Z-coordinate (Mandatory for Data Assimilation)	m
SATELE	elevation angle	deg
SATAZI	azimuth angle	deg
SATRES	satellite phase residuals	m
SATMPT	satellite multipath	m
FACDRY	dry mapping factor	-
FACWET	wet mapping factor	-
FACGRD	gradient mapping factor	-
FACTGD	gradient mapping factor for dry component	-
FACTGW	gradient mapping factor for wet component	-

¹Base unit is the reference unit for individual parameter scaling (see TROP/DESCRIPTION block).

APPENDIX I

SINEX_TRO File VERSION 2.00

DETAILED FORMAT DESCRIPTION

In this appendix, the following blocks are described:

1. Comment line (Optional)
2. Header and Footer Lines (Mandatory)
3. FILE/REFERENCE Block (Mandatory)
4. INPUT/FILES (for combined product only)
5. CENTERS/INFO_MODEL Block (for combined product only)
6. CENTERS/INFO_SOLUTION (for combined product only)
7. TROP/DESCRIPTION Block (Mandatory)
8. SITE/ID Block (Mandatory)
9. SITE/RECEIVER Block (Mandatory for GNSS)
10. SITE/ANTENNA Block (Mandatory for GNSS)
11. SITE/COORDINATES Block (Mandatory for GNSS)
12. SITE/ECCENTRICITY Block (Mandatory for GNSS)
13. SITE/GPS_PHASE_CENTER Block (Mandatory for GNSS)
14. TROP/SOLUTION Block (Mandatory for values in zenith directions)
15. SLANT/SOLUTION Block (Mandatory for values in slant directions)
1. Comment line (Optional)

Many blocks described in this appendix are in common with SINEX.

Some of them (as ANTENNA PHASE CENTER Block) are taken directly from SINEX 2.02 without any modifications. Others (as SITE/ID, SITE/RECEIVER, SITE/ECCENTRICITY, SITE/COORDINATES etc.) have slightly different description/format with respect to what reported in SINEX 2.02.

1. Comment line (Optional)

A comment line can be placed anywhere within or out from any block. It is limited to 80 characters in total with the starting '*' character of the line. The definition is following:

Field	Description	Format
Comment	Any general comment relevant to the SINEX_TRO file.	1H*,A79

2. Header and Footer Lines (Mandatory)

The Header line must be the first line in a SINEX_TRO file.

The Footer line must be the last line in a SINEX_TRO file.

Header Line		
Field	Description	Format
File Identifier	%=TRO	A5
Format Version	Four digits indicating the version of SINEX_TRO format used	1X,F4.2
File Agency Code	Identify the agency creating the file	1X,A3
Time	Creation time of this SINEX_TRO file defined as <u>year</u> : <u>day_of_the_year</u> : <u>sec_of_the_day</u> .	1X, <u>I4</u> .2, '!', <u>I3</u> .3, '!', <u>I5</u> .5
Agency Code	Identify the agency providing the data in the SINEX_TRO file	1X,A3
Start Time	Start time of solution in the this SINEX_TRO file	1X, <u>I4</u> .2, '!', <u>I3</u> .3, '!', <u>I5</u> .5

Naformátováno: Standardní písmo odstavce, Písmo: Tučné, Angličtina (USA), Kontrolovat pravopis a gramatiku

Naformátováno: Standardní písmo odstavce, Písmo: Tučné, Angličtina (USA), Kontrolovat pravopis a gramatiku

	<u>updated, and never reused, if the processing is modified in a way that might lead to a different error characteristics of the product. Mandatory for space geodetic techniques. Unique identifier of the product specific to a certain product or processing strategy. It must be updated, and never reused, if the processing is modified in a way that might lead to a different error characteristics of the product. Mandatory for space geodetic techniques.</u>	
Information	Relevant information for the type indicated by the previous field	1X,A60
		84

4. INPUT/FILES (for combined product only)

This block contains the list of the contributing solutions used in the combined product.

INPUT/FILES		
Field	Description	Format
Files	Name of contributing solutions	1X,A79

5. CENTERS/INFO_MODEL Block (for combined product only)

This block contains the information about the parameters used by the contributing Analysis Centers.

Center/Info_Model		
Field	Description	Format
Analysis Center	Name of Analysis Center	1X,A3
Observation Code	Observation technique used	1X,A1
Cut-off angle	Elevation cut-off angle used (<u>degreesdegrees</u>)	1X,I3
Data rate	Sampling rate for used data	1X,I4
Trop rate	Sampling rate for ALL trop estimates	1X,I4
Trop. Mapping function	TROP Mapping functions used	1X,A29
Grad. Mapping function	GRAD Mapping functions used	1X,A29
		80

6. CENTERS/INFO_SOLUTION (for combined product only)

This block contains for the site in the combined product file the information about the data and biases for the contributing Analysis Centers.

Center/Info_Solution		
Field	Description	Format
Site Code	Call sign for a site	1X,A9
Analysis Center	Name of Analysis Center	1X,A3
# of days	Number of days used by the AC	1X,I2
Day Code	Flag for each day (0 if not available, 1 otherwise)	1X,7I1
# of bias	Number of biases for the interval (1=weekly; 7=daily)	1X,I2

Biases	Biases for each day in [mm]	7(1X,F6.1)
		77

7. TROP/DESCRIPTION Block (Mandatory)

This block gives important parameters from the analysis and defines the fields in the block 'TROP/SOLUTION' and in the block 'SLANT/SOLUTION'.

TROP/DESCRIPTION		
Field	Description	Format
Information Type	Describes the type of information present in the next field. May take one of the following values:	1X,A29
	'TROPQ PARAMETER NAMES': Names of fields in trop solution (see Tables 6, 2 and 3) – mandatory with TROP/SOLUTION	n(1X,A6)
	'TROPQ PARAMETER UNITS': Units applied for individual fields in trop solution (see Table 1, 2 and 3). Each values reported in TROP/SOLUTION Block should be divided by the related TROPQ UNITS to get the base units – mandatory with TROP/SOLUTION	n(1X,A6)
	'TROPQ PARAMETER WIDTH': Width of fields in trop solution (see Tables 7, 2 and 3) – mandatory with TROP/SOLUTION	n(1X,A6)
	'SLANT PARAMETERS': Names of fields in slant solution (see Tables 4 and 5) – mandatory only with SLANT/SOLUTION	n(1X,A6)
	'SLANT PARAMETER UNITS': Units applied for individual fields in slant solution (see Tables 4 and 5) – mandatory only with SLANT/SOLUTION. Each values reported in SLANT/SOLUTION Block should be divided by the related SLANT UNITS to get the base units.	n(1X,A6)
	'SLANT PARAMETER WIDTH': Width of fields in slant solution (see Tables 4 and 5) – mandatory only with SLANT/SOLUTION	n(1X,A6)
	'DATA SAMPLING INTERVAL': Trop/Solution Original data Sampling Rate [sec]	1X,I22
	'TROPQ MODELING METHOD': (For GNSS only) Tropospheric estimation method: Filter, Smoother, Least Square, Piece Wise Linear Interpolation	1X,A22
	'GNSS SYSTEMS': (For GNSS only) Observation from GNSS system used (string concatenating system characters(G=GPS, R=GLONASS, E=Galileo, C=BeiDou)	1X,A22
	'REFRACTIVITY COEFFICIENTS': Factors used during conversion from ZPD into IWW.	1X, F5.2, 1X, F5.2, 1X, F8.1

	<p>'SOURCE OF MET/DATA': source of the surface meteorological observations used, it can be:</p> <ul style="list-style-type: none"> • OBS/LOCAL for on-site (local) meteo sensor 1X,A22 • OBS/NEARBY for nearby meteo data is used (with pressure adjusted for any GNSS site height difference) • OBS/INTERPOLATED: meteo data has been interpolated from a network of nearby stations • NWP/ccccctt data is from an NWP model where cccc is the (3-10 character) ID code for the NWP centre (e.g. ECMWF for ECMWF, METO for the Met Office, KNMI for KNMI, DWD for DWD, etc) and tt is the forecast lead time, e.g. 06 for a T+6hr forecast, 00 for an analysis). • NONE: not available 	
	<p>'OCEAN TIDE LOADING MODEL': <u>(For GNSS only)</u> Ocean tide loading model applied</p>	1X,A22
	<p>'ATMOSPHERIC TIDE LOADING MODEL': <u>(For GNSS only)</u> Atmospheric tide loading model applied</p>	1X,A22
	<p>'GEOID MODEL': Geoid model name for undulation values</p>	
	<p><u>Only for individual analysis centre submissions:</u></p>	1X,A22
	<p>'TROPOSPHERIC SAMPLING INTERVAL': Tropospheric parameter sampling interval [sec] – <u>mandatory with TROP/SOLUTION</u></p>	
	<p>'SLANT SAMPLING INTERVAL': Slant data sampling interval [sec] – <u>mandatory with SLANT/SOLUTION</u></p>	1X,I22
	<p>'A PRIORI TROPOSPHERE': A priori tropospheric model used</p>	1X,I22
	<p>'TROPO MAPPING FUNCTION': Name of mapping function used for mapping hydrostatic and wet delay-</p>	1X,A22
	<p>'GRADS MAPPING FUNCTION': Name of mapping function used for mapping horizontal gradients.</p>	1X,A22
	<p>'ELEVATION CUTOFF ANGLE': Elevation cut-off [deg]</p>	1X,A22
	<p><u>Only for combined solution:</u></p>	1X,F22
	<p>'BIAS FROM INTERVAL': Begin and end of interval for bias computation [yyddd]</p>	
	<p>'DELETE FACTOR': Limit (factor*sigma) for editing of trop estimates</p>	12X,I5,X,I5
		1X,F22
	The above fields may be in any order	
Information	Relevant information for the type indicated by the previous field	format is type-dependent
		Variable

8. SITE/ID Block (Mandatory)

This block provides general information for each site containing estimated parameters.

For NWP Data Assimilation it is mandatory to provide the coordinates of the observing site used to estimate the tropospheric parameters reported in the TROP/SOLUTION and/or in the SLANT/SOLUTION Block. The reported ellipsoid height and geoid height shall contain the antenna height in the SITE/ECCENTRICITY Block. These coordinates should be copied to BUFR.

SITE/ID		
Field	Description	Format
Site Code	Call sign for a site	1X,A9
Point Code	Physical monument used at a site	1X,A2
Unique Monument Identification	Unique alpha-numeric monument identification. For ITRF purposes it is a nine character DOMES/DOMEX number (five/six digits, followed by the single letter 'M' or 'S', followed by four/three digits)	1X,A9
Observation Code	Observation technique used.	1X,A1
Station Description	Free-format description of the site, typically the town and/or country	1X,A22
Approximate-Longitude	Approximate-Longitude of the site in degrees (-90° to 90°NE/+), (decimals), minutes and seconds	1X,I3,1X,I2,1X,F4.1F102.6
Approximate-Latitude	Approximate-Latitude of the site in degrees (0° to 360°E) (E/+), minutes and seconds, (decimals)	1X,I3,1X,I2,1X,F4.1F102.6
Approximate Ellipsoidal-Height	Approximate-Height above ellipsoid of the site in metres	1X,F9912.3
Approximate-Geoid-Height	Approximate-Height above geoid of the site in metres	1X,F99.3
		92

9. SITE/RECEIVER Block (Mandatory for GNSS)

List the receiver used at each site during the observation period of interest.

SITE/RECEIVER		
Field	Description	Format
Site Code	Call sign for a site	1X,A9
Point Code	Physical monument used at a site	1X,A2
Solution ID	Solution Number at a Site/Point code for which some parameters are estimated	1X,A4
Observation Code	Observation technique used.	1X,A1
Start Time	Time since the receiver has been operating at the Site/Point defined as year:day_of_the_year:sec_of_the_day. Value 00:000:00000 indicates that the receiver has been operating at least since the "File Epoch Start Time"	1X,I42.2, 1H:,I3.3, 1H:,I5.5

End Time	Time since the receiver has been operating at the Site/Point defined as <i>yyyear</i> : <i>day_of_the_year</i> : <i>sec_of_the_day</i> . Value 00:000:00000 indicates that the receiver has been operating at least since the "File Epoch End Time"	1X, 14 .2, 1H;:13.3, 1H;:15.5
Receiver Type	Receiver Name & model	1X,A20
Receiver Serial Number	Serial number of the receiver. Takes on value '-----' if unknown	1X,A20
Receiver Firmware	Firmware used by this receiver during the epoch specified above. Takes on value '-----' if unknown	1X,A11
		100

10. SITE/ANTENNA Block (Mandatory for GNSS)

List of antennas used at each site used in the SINEX_TRO file.

SITE/ANTENNA		
Field	Description	Format
Site Code	Call sign for a site	1X,A9
Point Code	Physical monument used at a site	1X,A2
Solution ID	Solution Number at a Site/Point code for which some parameters are estimated	1X,A4
Observation Code	Observation technique used.	1X,A1
Start Time	Time since the antenna has been installed at the Site/Point defined as <i>yyyear</i> : <i>day_of_the_year</i> : <i>sec_of_the_day</i> . Value 00:000:00000 indicates that the receiver has been operating at least since the "File Epoch Start Time"	1X, 14 .2, 1H;:13.3, 1H;:15.5
End Time	Time since the antenna has been installed at the Site/Point defined as <i>yyyear</i> : <i>day_of_the_year</i> : <i>sec_of_the_day</i> . Value 00:000:00000 indicates that the receiver has been operating at least since the "File Epoch End Time"	1X, 14 .2, 1H;:13.3, 1H;:15.5
Antenna Type	Antenna Name & model	1X,A20
Antenna Serial Number	Serial number of the antenna. Takes on value '-----' if unknown	1X, A20
		88

11. SITE/COORDINATES Block (Mandatory for GNSS)

This block provides the coordinates of the sites. ECCENTRICITY should be applied to these precise coordinates. The coordinates should be related to SITE point and only if ECCENTRICITIES are ZERO, then it is the ARP point. For the combination result, it also gives some statistical information.

SITE/COORDINATES

Field	Description	Format
Site Code	Call sign for a site	1X,A9
Point Code	Physical monument used at a site	1X,A2
Solution ID	Solution number to which the input in this data line is referred to	1X,A4
Observation Code	Observation technique used	1X,A1
Data Start	Start Time since the site coordinates are valid, defined as year :day_of_the_year:sec_of_the_day. Value 00:000:00000 indicates the validity since the "File Epoch Start Time"	1X,I4.2, 1H:;I3.3, 1H:;I5.5
Data End	END Time since the site coordinates are valid, defined as year :day_of_the_year:sec_of_the_day. Value 00:000:00000 indicates the validity till the "File Epoch End Time"	1X,I4.2, 1H:;I3.3, 1H:;I5.5
Coordinates	x,y,z-coordinate of a site of SINEX_TRO format used. These coordinates should be copied to BUBF.	3(1X,F12.3)
System	Terrestrial Reference System Code	1X,A6
Remark	A remark used to identify the origin of the coordinates (AC acronym or 'Mean')	1X,A5
Standard Deviation	Standard deviation for x,y,z in [mm] (Used only for Mean)	3(1X,I2)
Counter	Number of ACs used for Mean(Used only for Mean)	1X,I2
		110

12. SITE/ECCENTRICITY Block (~~Optional, if not provided assumed null~~ Mandatory for GNSS)

List of antenna eccentricities from the Marker to the Antenna Reference Point (ARP) or to the intersection of axis.

SITE/ECCENTRICITIES		
Field	Description	Format
Site Code	Call sign for a site	1X,A9
Point Code	Physical monument used at a site	1X,A2
Solution ID	Solution Number at a Site/Point code for which some parameters are estimated	1X,A4
Observation Code	Observation technique used.	1X,A1
Start Time	Time since the antenna has been installed at the Site/Point defined as year :day_of_the_year:sec_of_the_day. Value 00:000:00000 indicates that the receiver has been operating at least since the "File Epoch Start Time"	1X,I4.2, 1H:;I3.3, 1H:;I5.5
End Time	Time since the antenna has been installed at the Site/Point defined as year :day_of_the_year:sec_of_the_day. Value 00:000:00000 indicates that the receiver has been operating at least since the "File Epoch End Time"	1X,I4.2, 1H:;I3.3, 1H:;I5.5
Eccentricity Reference System	Reference system used to describe vector distance from monument benchmark to the antenna reference point or intersection of axis: 'UNE' - Local reference system: Up, North, East 'XYZ' - Cartesian Reference System X, Y, Z.	1X,A3

	All units are in meters	
Up / X Eccentricity	Up / X offset from the marker to the Antenna reference point (ARP)	1X,F8.4
North / Y Eccentricity	North/Y offset from the marker to the Antenna reference point (ARP)	1X,F8.4
East / Z Eccentricity	East / Z offset from the marker to the Antenna reference point (ARP)	1X,F8.4
		77

13. SITE/ANTENNA-GPS_PHASE-PHASE_CENTER Block (Mandatory for GNSS)

Reference to the antenna phase center model that was used for satellite and receiver antennas.

Field	Description	Format
Antenna Type	Antenna name & model. May be blank to indicate the antenna calibration model that was applied in general. Exceptions need to be specified in separate lines (to be specified individual calibrations for some of the receiver antennas have been used or satellite calibrations are taken from specific source).	1X,A20
Antenna Serial Number	Serial number of the antenna. May be blank if not relevant, e.g., if the same antenna calibration model is applied to all antennas of this type.	1X,A20
Antenna Calibration Model	Name of the antenna model used in the correction of the observations for phase center variations	1X,A10
		53

Comments:

- For IGS the antenna calibration model refers to the ANTEX file provided by the IGS Central Bureau Information System:

directory: <ftp://igsb.jpl.nasa.gov/igsb/station/general>
 atx ('www' for GPS week of the last update)

- For IGS standard antenna names please refer to ftp://igsb.jpl.nasa.gov/igsb/station/general/rcvr_ant.tab

- If a receiver antenna is given in this block with a serial number to indicate individual antenna calibration model it has to be assigned in the SITE/ANTENNA Block to a specific station.

14. TROP/SOLUTION Block (Mandatory for values in zenith directions)

This block contains the solution for all epochs.

TROP/SOLUTION		
Field	Description	Format
Marker	Name of the marker	1X,A9

	NOTE : For backward compatibility left - aligned 4-character station codes are also permitted	
Time	Time epoch of the solution: Middle of data Interval, defined as <u>yy</u> year:day_of_the_year:sec_of_the_day.	1X,I42.2, ':',I3.3,':',I5.5
Values	Space separated fields of variable length. Number and order of fields are given in the block TROP/DESCRIPTION. Readable by: read(line(20:,*))(val(i),i=1,n)	no format
		variable

15. SLANT/SOLUTION Block (~~Optional~~Mandatory for values in slant directions)

This block contains the slant solution for all epochs.

SLANT/SOLUTION		
Field	Description	Format
Marker	Name of the marker NOTE : For backward compatibility left - aligned 4-character station codes are also permitted	1X,A9
Time	Time epoch of the solution: Middle of data Interval defined as <u>year</u> yy:day_of_the_year:sec_of_the_day.	1X,I42.2, ':',I3.3,':',I5.5
Values	Space separated fields of variable length. Number and order of fields are given in the block TROP/DESCRIPTION. Readable by: read(line(20:,*))(val(i),i=1,n)	no format
		variable

APPENDIX II

1. Example for Submissions of Trop & Slant Estimates

```

#TRO 2.00 GOP 17:120:74028 GOP 13:168:64500 13:168:86100 P MIX
-----
*FILE/REFERENCE
*INFO TYPE INFO
DESCRIPTION GOP = Geodetic Observatory Pecny, RIGTC
CITY/ST Solution parameters
CONTACT gnss@peeny.cz
SOFTWARE G-Nut/Geb
INPUT GNSS/RAW data
Version Number 001
-----
*FILE/REFERENCE
*TROPO/DESCRIPTION
*KEYWORD VALUE(S)
TROPO SAMPLING INTERVAL 300
SLANT SAMPLING INTERVAL 300
DATA SAMPLING INTERVAL 300
GNSS SYSTEMS G
TROPO MODELING METHOD KALMAN FILTER
GEIOD MODEL VMF1/EGM96
OCEAN TIDE LOADING MODEL RES2004
ATMOSPHERIC TIDE LOADING MODEL NOT APPLIED
ELEVATION CUTOFF ANGLE 7 DEG
OBSERVATION WEIGHTING SINEW
A PRIORI TROPOSPHERE EXTERN
TROPO MAPPING FUNCTION GMP
GRASS MAPPING FUNCTION CHEN HERRING
REFRACTIVITY COEFFICIENTS 77.60 70.40 373900.0
SOURCE OF MET/DATA NWS
TROPO PARAMETER NAMES TROTOT STDEV TRODRY TROWET TGTOT STDEV TGETOT STDEV NSAT GOPD IWV PRESS TEMDRY WMTBMP TEMPLS WMTLFS ZWDDEC
TROPO PARAMETER UNITS 1e+03 1e+03 1e+03 1e+03 1e+03 1e+03 1 1 1 1 1 1 1e+03 1e+03 1
SLANT PARAMETER WIDTHS 6 6 6 6 6 6 6 4 4 6 7 6 6 6 6 6
SLANT PARAMETER NAMES SLTSTOT STDEV SLTDRY SLTWET SLTIWV SLTGRD SATRES SATMPT SAT SATELE SATELE1 FACDRY FACWET FACGRD
SLANT PARAMETER UNITS 1e+03 1e+03 1e+03 1e+03 1 1e+03 1e+03 1e+03 1 1 1 1 1 1 1
SLANT PARAMETER WIDTHS 8 6 8 6 6 6 6 6 4 7 7 9 9 9 9
-----
*SITE/ID
*STATION PT DOME T STATION DESCRIPTION APPROX LON APPROX LAT APP H GEIOD HGT
GOPE A 1 P 13:168:64500 13:168:86100 3979315.993 1050312.623 4857067.191 IGS08 GOP
WTRR A 1 P 13:168:64500 13:168:03300 4075580.457 931853.932 4801668.218 IGS08 GOP
ZIMM A 1 P 13:168:00300 13:168:86100 4331296.936 567556.035 4633134.023 IGS08 GOP
-----
*TROPO/STA COORDINATES
*STATION PT SOLN T DATA START DATA END STA X STA Y STA Z SYSTEM REMRK
GOPE A 1 P 13:168:64500 13:168:86100 3979315.993 1050312.623 4857067.191 IGS08 GOP
WTRR A 1 P 13:168:64500 13:168:03300 4075580.457 931853.932 4801668.218 IGS08 GOP
ZIMM A 1 P 13:168:00300 13:168:86100 4331296.936 567556.035 4633134.023 IGS08 GOP
-----
*TROPO/STA COORDINATES
*SITE/ECCENTRICITY
*STATION PT SOLN T DATA START DATA END UP NORTH EAST
GOPE A 1 P 13:168:64500 13:168:86100 UNE 0.1114 0.0000 0.0000
WTRR A 1 P 13:168:64500 13:168:86100 UNE 0.0710 0.0000 0.0000
ZIMM A 1 P 13:168:64500 13:168:86100 UNE 0.0000 0.0000 0.0000
-----
*SITE/ANTENNA
*STATION PT SOLN T DATA START DATA END DESCRIPTION S/N
GOPE A 1 P 13:168:64500 13:168:86100 TPSCR.G3 FSR6
WTRR A 1 P 13:168:64500 13:168:86100 LEIAR25.R3 LEI1
ZIMM A 1 P 13:168:64500 13:168:86100 TRM29659.00 NONE
-----
*SITE/RECEIVER
*STATION PT SOLN T DATA START DATA END DESCRIPTION S/N FIRMW
GOPE A 1 P 13:168:64500 13:168:86100 TPS NETC3 ---
WTRR A 1 P 13:168:64500 13:168:86100 LEICA GRX1200+GNSS ---
ZIMM A 1 P 13:168:64500 13:168:86100 TRIMBLE NETRS ---
-----
*TROPO/SOLUTION
*STATION EPOCH TROTOT STDEV TRODRY TROWET TGTOT STDEV TGETOT STDEV NSAT GOPD IWV PRESS TEMDRY WMTBMP TEMPLS WMTLFS ZWDDEC
GOPE 13:168:64500 2334.3 5.3 2166.8 167.4 1.00 0.84 0.14 0.93 7 2.2 27.26 951.90 299.6 285.7 7.20 7.21 3.32
GOPE 13:168:64800 2334.2 5.2 2166.8 167.4 1.00 0.84 0.17 0.92 6 1.9 27.25 951.90 299.6 285.7 7.20 7.21 3.32
GOPE 13:168:65100 2333.0 5.1 2166.8 166.2 1.00 0.83 0.29 0.91 7 2.2 27.06 951.90 299.6 285.7 7.20 7.21 3.33
GOPE 13:168:65400 2333.3 5.0 2166.8 166.6 1.15 0.81 0.43 0.90 7 2.1 27.12 951.90 299.5 285.7 7.19 7.21 3.34
...
ZIMM 13:168:85200 2271.6 4.7 2081.4 192.2 -0.26 0.71 0.76 0.89 10 1.2 30.97 913.89 296.4 282.6 7.24 6.76 2.94
ZIMM 13:168:85500 2274.9 4.5 2081.4 193.5 -0.21 0.67 0.79 0.86 10 1.2 31.17 913.93 296.3 282.6 7.23 6.75 2.94
ZIMM 13:168:85800 2275.0 4.6 2081.5 193.5 -0.18 0.65 0.79 0.86 9 1.1 31.16 913.97 296.3 282.6 7.21 6.74 2.94
ZIMM 13:168:86100 2274.7 4.7 2081.5 193.2 -0.20 0.66 0.84 0.85 8 1.4 31.11 914.01 296.2 282.5 7.20 6.74 2.94
-----
*SLANT/SOLUTION
*STATION EPOCH SLTSTOT STDEV SLTDRY SLTWET SLTIWV SLTGRD SATRES SATMPT SAT SATELE SATELE1 FACDRY FACWET FACGRD
GOPE 13:168:64500 8363.0 9.9 7748.2 603.3 98.2 10.4 1.1 0.0 G05 16.000 39.323 3.57822 3.60322 12.159794
GOPE 13:168:64500 5635.5 6.2 5226.3 405.1 66.0 -0.2 4.2 0.0 G06 24.340 276.596 2.411963 2.419605 5.273237
GOPE 13:168:64500 3527.2 6.5 3266.0 252.6 41.1 0.8 7.8 0.0 G16 41.483 305.307 1.507287 1.508554 1.698072
GOPE 13:168:64500 2462.1 5.4 2297.0 177.5 28.9 -0.4 -12.1 0.0 G21 70.591 178.293 1.060091 1.060178 0.373115
GOPE 13:168:64500 3421.8 6.3 3151.5 243.7 39.7 0.5 26.1 0.0 G29 43.362 80.861 1.454446 1.455519 1.534643
GOPE 13:168:64500 6113.0 8.5 5685.3 441.0 71.8 -5.5 -7.8 0.0 G31 22.233 217.773 2.623783 2.633921 6.334319
GOPE 13:168:64800 8936.7 10.2 8283.6 645.5 105.1 12.5 -4.8 0.0 G05 14.907 37.658 3.822962 3.856815 13.951109
GOPE 13:168:64800 5243.0 7.8 4872.2 377.3 61.4 -0.1 -6.3 0.0 G06 26.264 277.755 2.248554 2.254558 4.513417
...
ZIMM 13:168:85800 6442.8 7.7 5897.9 550.7 88.7 -6.0 0.1 0.0 G28 20.481 282.065 2.833525 2.846356 7.469034
ZIMM 13:168:85800 2399.2 4.7 2183.1 202.9 32.7 -0.2 13.4 0.0 G32 72.429 233.060 1.048811 1.048880 0.331808
ZIMM 13:168:86100 2382.3 4.8 2167.6 201.2 32.4 -0.2 13.7 0.0 G01 73.779 315.070 1.043149 1.044006 0.302685
ZIMM 13:168:86100 2291.3 4.7 2114.2 196.2 31.6 0.1 -19.2 0.0 G11 79.911 145.618 1.015666 1.015687 0.180618
ZIMM 13:168:86100 4152.9 6.3 3805.3 353.7 57.0 1.6 -7.8 0.0 G14 33.055 54.604 1.828113 1.830890 2.792066
ZIMM 13:168:86100 8613.9 9.1 7878.8 737.5 118.8 -9.6 7.1 0.0 G17 15.066 318.644 3.785092 3.817334 13.667947
ZIMM 13:168:86100 4314.8 6.4 3961.7 368.3 59.3 1.3 -16.5 0.0 G19 31.583 165.036 1.903249 1.906485 3.075190
ZIMM 13:168:86100 3388.6 5.7 3097.0 287.7 46.3 -1.1 5.1 0.0 G20 42.154 245.512 1.487814 1.489987 1.637305
ZIMM 13:168:86100 6721.5 8.0 6146.0 573.3 82.3 -7.0 9.3 0.0 G28 19.603 279.934 2.952592 2.967259 8.150843
ZIMM 13:168:86100 2366.6 4.7 2156.7 200.2 32.2 -0.2 9.8 0.0 G32 74.810 235.655 1.036111 1.036160 0.281091
-----
#ENDTRO

```

2. Example for Combination Product

```
%TRO 2.00 ASI 15:352:42300 EUR 15:298:01800 15:304:84600 P MIX
-----
+FILE/REFERENCE
DESCRIPTION Weekly combination of trop estimates of EPN Analysis Centers
OUTPUT Combined Tropospheric Products of the EPN Network
CONTACT rosa.pacione@geos.it,ASI/CGS Italy
Version Number 001
-----
+TROP/DESCRIPTION
*
KEYWORD VALUE(S)
TROPO SAMPLING INTERVAL 3600
BIAS FROM INTERVAL 15298 15304
DELETE FACTOR 1.0
GEOID MODEL EGM2008
TROPO PARAMETER NAMES TROTOT STDDEV #ACTAK #ACDEL
TROPO PARAMETER UNITS 1.0e+3 1.0e+3 0.0e+0 0.0e+0
TROPO PARAMETER WIDTH 8 8 2 2
-----
+CENTERS/INFO_MODEL
* AC T CUT DATA TROP TROP_MAPPING_FUNCTION
ASI P 3 300 3600 VMF1
BEK P 3 180 3600 WET GMF
BKG P 3 180 3600 WET GMF
COE P 3 180 3600 WET VMF
-----
-CENTERS/INFO_MODEL
-----
+INPUT/FILES
ASILOPEFIN_2015102500_01D_01H.TRO
-----
ASILOPEFIN_2015103100_01D_01H.TRO
BEKLOPEFIN_2015102500_01D_01H.TRO
-----
BEKLOPEFIN_2015103100_01D_01H.TRO
-----
COELOPEFIN_2015103100_01D_01H.TRO
-----
-INPUT/FILES
-----
+FILE/COMMENT
Coordinates taken from EUREF weekly combined solution
-----
-FILE/COMMENT
-----
+SITE/ID
*STATION PT DOMES T STATION DESCRIPTION APPROX_LON APPROX_LAT APP_HGT GEOID_HGT
ACOR A 13434M001 P A Coruna, ES 351 36 3.9 43 21 51.8 66.900 14.821
-----
-SITE/ID
-----
+SITE/COORDINATES
*STATION PT SOLN T DATA_START DATA_END STA_X STA_Y STA_Z SYSTEM REMRK SX SY SZ #N
ACOR A 1 P 15:298:00000 15:304:86370 4594489.598 -678367.524 4357066.243 ITRF08 Mean 0 0 0
-----
-SITE/COORDINATES
-----
+SITE/RECEIVER
*STATION PT SOLN T DATA_START DATA_END DESCRIPTION S/N FIRMWARE
ACOR A 1 P 15:298:00000 15:304:86370 LEICA GRX1200PRO -459187 8.20/2.125
-----
-SITE/RECEIVER
-----
+SITE/ANTENNA
*STATION PT SOLN T DATA_START DATA_END DESCRIPTION S/N
ACOR A 1 P 15:298:00000 15:304:86370 LEIAT504 LEIS -103033
-----
-SITE/ANTENNA
-----
+ANTENNA_PHASE_CENTER
*ANTENNA TYPE S/N CALIBRATION MODEL
igs08_1885
- ANTENNA_PHASE_CENTER-----
+SITE/ECCENTRICITY
*
*STATION PT SOLN T DATA_START DATA_END UP NORTH EAST
AXE REF->BENCHMARK(M)
ACOR A 1 P 15:298:00000 15:304:86370 UNE 3.0460 0.0000 0.0000
-----
-SITE/ECCENTRICITY
-----
+TROP/SOLUTION
*STATION EPOCH TROTOT SIG #T #D
ACOR 15:298:01800 2461.6 5.6 4 0
ACOR 15:298:05400 2461.6 4.3 4 0
ACOR 15:298:09000 2457.8 4.6 4 0
-----
-TROP/SOLUTION
-----
+CENTERS/INFO_SOLUTION
*STATION AC #D DAT COD #B BIAS BIAS BIAS BIAS BIAS BIAS
ACOR BEK 7 1111111 1 1.4 1.0 0.9 1.3 1.1 1.0 1.2
ACOR IGE 7 1111111 1 1.9 1.9 1.9 1.9 1.9 1.9 1.9
ACOR IGN 6 1110111 1 1.9 1.5 1.3 1.8 2.0 1.6 1.9
ACOR ROB 4 1001101 1 -5.3 -5.0 -5.1 -5.5 -5.3 -4.9 -5.2
-----
-CENTERS/INFO_SOLUTION
-----
%=ENDTRO
```

3. Example of Submission for Radiosonde Product

```

%=TRO 2.00 GOP 17:120:73990 GOP 13:169:00000 13:181:21600 S MIX
-----
+FILE/REFERENCE
*INFO TYPE          INFO
DESCRIPTION         GOP - Geodetic Observatory Pecny, RIGTC
OUTPUT              Solution parameters
CONTACT             gns@pecny.cz
SOFTWARE            G-Nut/Rao
INPUT              GNS/NNW/RAO/OZH data
-FILE/REFERENCE
-----
+TROP/DESCRIPTION
*
KEYWORD
TROPO SAMPLING INTERVAL          VALUE(S)
REFRACTIVITY COEFFICIENTS      77.6 70.4 373900.0
TROPO PARAMETER NAMES          WVPDEC WMTLPS TEMPLS ZWDDC WVPRES SCLHGT IWV PRESS HUMSPC TEMDRY WMTMP TRODRY TROTOT TROWET
TROPO PARAMETER UNITS          1 1e+03 1e+03 1 1 0.001 1 1 1 1 1 1e+03 1e+03 1e+03
TROPO PARAMETER WIDTH          6 6 6 6 6 6 6 7 6 6 6 6 6 6
-TROP/DESCRIPTION
-----
+SITE/ID
*STATION PT DOME S T STATION DESCRIPTION APPROX_LON APPROX_LAT APP_H GEODID HGT
EZM 11520 A XXXXXXXX S Czech Republic: PRAHA- 14 26 48.8 50 0 28.1 340.0 38.003
-SITE/ID
-----
+SITE/COORDINATES
+SITE/COORDINATES
EZM 11520 A 1 S 13:169:00000 13:181:21600 3977538.400 1024729.503 4863607.154 IGS08 GOP
+SITE/COORDINATES
-----
+TROP/SOLUTION
*STATION EPOCH WVPDEC WMTLPS TEMPLS ZWDDC WVPRES SCLHGT IWV PRESS HUMSPC TEMDRY WMTMP TRODRY TROTOT TROWET
EZM 11520 13:169:00000 2.99 7.11 7.05 3.73 18.87 8.155 32.19 980.00 12.064 294.5 287.8 2230.6 2426.9 196.3
EZM 11520 13:169:21600 3.36 6.97 7.13 3.50 21.27 8.164 28.78 981.00 13.600 295.3 286.9 2232.9 2409.0 176.0
EZM 11520 13:169:43200 3.05 7.22 7.44 3.64 23.94 8.164 34.14 980.00 15.337 305.5 288.7 2230.7 2438.2 207.6
EZM 11520 13:170:00000 5.19 6.94 7.15 3.27 23.21 8.043 29.11 982.00 14.835 294.8 286.6 2235.2 2413.4 178.2
EZM 11520 13:170:21600 4.55 6.59 7.02 3.00 22.78 8.086 29.56 982.00 14.559 296.8 284.9 2235.2 2417.3 182.1
EZM 11520 13:170:43200 3.43 7.05 7.32 4.10 26.41 8.112 36.86 981.00 16.918 304.1 288.8 2232.9 2456.9 224.0
EZM 11520 13:171:00000 4.02 7.37 7.03 4.73 22.78 8.118 29.36 978.00 14.619 297.3 290.5 2226.1 2403.5 177.4
EZM 11520 13:171:21600 3.84 7.19 6.86 4.07 22.36 8.195 28.93 978.00 14.347 296.9 288.4 2226.1 2402.1 176.0
EZM 11520 13:171:43200 3.57 7.31 7.42 4.24 25.46 8.160 33.76 977.00 16.370 304.5 290.1 2223.8 2428.1 204.2
EZM 11520 13:172:00000 2.10 6.56 6.64 2.87 16.60 8.161 32.20 976.00 10.647 293.8 284.4 2221.5 2420.2 186.6
EZM 11520 13:172:21600 2.02 5.82 6.15 3.10 16.39 8.142 30.38 979.00 10.477 291.9 281.7 2228.3 2417.5 189.2
EZM 11520 13:172:43200 2.80 6.24 6.45 3.50 16.39 8.124 24.22 980.00 10.466 297.5 282.9 2230.6 2380.8 150.2
EZM 11520 13:173:00000 2.30 5.67 6.30 2.45 16.82 8.094 26.38 982.00 10.720 292.9 280.3 2235.2 2400.3 165.1
EZM 11520 13:173:21600 2.48 5.78 6.06 2.72 16.82 8.084 24.83 982.00 10.720 292.1 279.4 2235.2 2391.0 155.9
EZM 11520 13:173:43200 2.03 6.02 6.82 3.28 12.94 8.054 25.87 981.00 8.244 297.9 280.9 2232.9 2394.4 161.5
EZM 11520 13:174:00000 2.43 5.97 6.42 3.48 16.39 8.043 29.36 980.00 10.466 291.8 280.6 2230.6 2414.1 183.5
EZM 11520 13:174:21600 2.80 5.67 6.19 3.27 16.92 7.991 25.55 979.00 10.823 291.5 279.5 2228.3 2388.7 160.4
EZM 11520 13:174:43200 2.42 5.60 6.24 2.96 15.56 7.993 28.94 979.00 9.944 294.8 278.6 2228.3 2410.5 182.2
EZM 11520 13:175:00000 1.88 5.19 6.16 2.04 10.72 7.908 22.74 981.00 6.822 290.1 273.9 2232.8 2378.4 145.6
EZM 11520 13:175:21600 1.92 5.22 6.12 2.11 12.85 7.842 24.83 982.00 8.181 285.5 272.5 2235.1 2394.8 159.7
EZM 11520 13:175:43200 2.17 5.16 5.96 2.21 13.46 7.867 26.26 983.00 8.564 287.3 273.0 2237.4 2406.1 168.7
EZM 11520 13:176:00000 2.00 5.21 6.06 2.21 13.46 7.816 26.73 982.00 8.572 285.1 272.7 2235.1 2406.9 171.8
EZM 11520 13:176:21600 2.38 4.92 6.16 2.24 13.11 7.740 24.14 981.00 8.355 285.1 272.1 2232.8 2388.4 155.5
EZM 11520 13:176:43200 2.36 4.73 5.93 2.37 12.77 7.780 22.98 983.00 8.118 285.3 271.0 2237.4 2386.0 148.6
EZM 11520 13:177:00000 2.26 4.88 5.99 2.48 10.86 7.757 20.63 986.00 6.881 283.3 270.3 2244.2 2378.0 133.8
EZM 11520 13:177:21600 2.37 4.94 6.07 2.62 11.09 7.755 20.91 986.00 7.023 282.9 270.2 2244.2 2378.8 135.6
EZM 11520 13:177:43200 2.24 5.18 5.92 2.51 10.08 7.774 19.82 988.00 6.368 284.3 270.2 2248.7 2377.3 128.6
EZM 11520 13:178:00000 4.09 6.25 6.16 4.34 9.74 7.820 13.10 990.00 6.139 282.5 273.2 2253.3 2337.3 84.1
EZM 11520 13:178:21600 4.48 5.83 6.60 4.47 10.29 7.751 13.26 989.00 6.494 283.9 273.2 2251.0 2336.1 85.1
EZM 11520 13:178:43200 2.95 5.82 6.79 4.16 9.34 7.715 14.36 988.00 5.901 287.1 273.9 2248.7 2340.7 91.9
EZM 11520 13:179:00000 4.18 5.94 6.86 3.94 10.22 7.794 13.20 987.00 6.463 281.8 274.3 2246.4 2330.8 84.4
EZM 11520 13:179:21600 3.16 5.68 6.58 3.12 10.50 7.800 14.60 986.00 6.649 281.5 272.5 2244.2 2338.1 93.9
EZM 11520 13:179:43200 2.55 5.81 7.04 3.06 9.60 7.789 14.39 985.00 6.086 292.5 273.6 2241.9 2334.1 92.2
EZM 11520 13:180:00000 3.15 6.12 6.64 4.04 11.24 7.887 16.34 984.00 7.134 284.1 276.1 2239.6 2343.4 103.8
EZM 11520 13:180:21600 2.70 5.93 6.39 3.08 11.24 7.827 18.31 983.00 7.141 285.5 273.6 2237.4 2354.7 117.3
EZM 11520 13:180:43200 2.04 5.67 6.87 3.42 10.72 7.798 21.14 981.00 6.822 292.1 273.6 2232.8 2368.3 135.5
EZM 11520 13:181:00000 2.79 5.90 6.42 3.42 13.11 7.828 22.46 984.00 8.330 285.8 275.5 2239.6 2382.6 143.0
EZM 11520 13:181:21600 6.51 5.82 5.77 6.32 9.41 7.775 9.06 986.00 5.955 283.8 273.9 2244.2 2302.2 58.0
-TROP/SOLUTION
%=ENDTRO

```

4. Example of Submission for NWM-derived Parameters

```

%=TRO 2.00 GOP 17:120:63556 GOP 13:168:00000 13:169:00000 N MIX
-----
+FILE/REFERENCE
*INFO TYPE          INFO
DESCRIPTION         GOP - Geodetic Observatory Pecny, RIGTC
OUTPUT              Solution parameters
CONTACT             gns@pecny.cz
SOFTWARE            G-Nut/Shu
INPUT               GNSS/NWM/RAO/OZH data
-FILE/REFERENCE
-----
+TROP/DESCRIPTION
*KEYWORD            VALUE(S)
TROP SAMPLING INTERVAL          3600
REFRACTIVITY COEFFICIENTS      77.60 70.40 373900.0
TROP PARAMETER NAMES           WVPDCC WMTLPS TEMPLS ZWDDEC WVPRES SCLHGT IWV PRESS HUMSPC TEMDRY WTEMP TRODRY TROTOT TROWET
TROP PARAMETER UNITS           1 1e+03 1e+03 1 1 0.001 1 1 1 1 1 1e+03 1e+03 1e+03
TROP PARAMETER WIDTH           6 6 6 6 6 6 6 6 6 6 6 6 6 6 6
-TROP/DESCRIPTION
-----
+SITE/ID
*STATION   PT   DOMES   T   STATION DESCRIPTION   APPROX_LON APPROX_LAT   APP_H   GROID_HGT
GOPE      A 13020002 N          14 47 8.2 49 54 49.3 952.8 377.786
WTRR      A 14201M010 N         12 52 44.1 49 8 39.1 666.7 39.605
Z1MM      A 14001M004 N         7 27 55.0 46 52 37.6 957.0 43.733
-SITE/ID
-----
+SITE/COORDINATES
*STATION   PT   N   E   U   STATION DESCRIPTION   APPROX_LON APPROX_LAT   APP_H   GROID_HGT
GOPE      A 1 N 13:168:00000 13:169:00000 3979316.100 1050312.600 4857067.400 IGS08 GOP
WTRR      A 1 N 13:168:00000 13:169:00000 4075580.800 931853.900 4801568.800 IGS08 GOP
Z1MM      A 1 N 13:168:00000 13:169:00000 4331297.300 567556.000 4633134.600 IGS08 GOP
-SITE/COORDINATES
-----
+TROP/SOLUTION
*STATION   EPOCH   WVPDCC WMTLPS TEMPLS ZWDDEC WVPRES SCLHGT IWV PRESS HUMSPC TEMDRY WTEMP TRODRY TROTOT TROWET
GOPE      13:168:00000 2.58 6.23 6.51 2.80 12.51 8.081 22.67 953.04 8.202 293.1 280.1 2169.4 2311.4 142.0
GOPE      13:168:03600 2.49 6.21 6.50 2.74 12.21 8.081 22.79 953.13 8.006 292.7 279.9 2169.6 2312.5 142.9
GOPE      13:168:07200 2.41 6.18 6.49 2.68 11.91 8.082 22.92 953.22 7.810 292.4 279.8 2169.8 2313.6 143.7
GOPE      13:168:10800 2.33 6.16 6.48 2.62 11.61 8.082 23.05 953.32 7.614 292.1 279.7 2170.0 2314.6 144.6
GOPE      13:168:14400 2.24 6.13 6.47 2.57 11.31 8.082 23.17 953.41 7.418 291.8 279.5 2170.2 2315.7 145.5
GOPE      13:168:18000 2.16 6.11 6.46 2.51 11.02 8.082 23.30 953.50 7.222 291.4 279.4 2170.5 2316.8 146.3
GOPE      13:168:21600 2.08 6.08 6.45 2.45 10.72 8.082 23.42 953.59 7.026 291.1 279.3 2170.7 2317.8 147.2
GOPE      13:168:25200 2.11 6.17 6.52 2.52 11.23 8.089 23.79 953.60 7.361 291.9 279.8 2170.7 2319.9 149.2
GOPE      13:168:28800 2.18 6.30 6.62 2.64 11.97 8.098 24.24 953.57 7.847 293.0 280.5 2170.6 2322.2 151.6
GOPE      13:168:32400 2.27 6.45 6.74 2.77 12.84 8.109 24.74 953.51 8.418 294.3 281.3 2170.5 2324.7 154.2
GOPE      13:168:36000 2.36 6.60 6.86 2.92 13.74 8.120 25.27 953.42 9.010 295.6 282.2 2170.3 2327.4 157.1
GOPE      13:168:39600 2.44 6.75 6.97 3.06 14.57 8.131 25.81 953.30 9.556 296.9 283.1 2170.0 2330.0 160.0
GOPE      13:168:43200 2.50 6.89 7.06 3.17 15.23 8.141 26.34 953.15 9.992 298.0 283.8 2169.7 2332.5 162.9
GOPE      13:168:46800 2.46 6.97 7.12 3.22 15.38 8.149 26.83 952.95 10.096 298.7 284.3 2169.2 2334.8 165.6
GOPE      13:168:50400 2.40 7.05 7.16 3.25 15.37 8.155 27.31 952.73 10.091 299.2 284.7 2168.7 2337.1 168.4
GOPE      13:168:54000 2.33 7.10 7.19 3.26 15.27 8.161 27.78 952.49 10.031 299.5 285.0 2168.2 2339.3 171.1
GOPE      13:168:57600 2.26 7.15 7.21 3.27 15.16 8.166 28.23 952.26 9.966 299.7 285.3 2167.7 2341.3 173.7
GOPE      13:168:61200 2.21 7.19 7.21 3.29 15.12 8.171 28.65 952.05 9.950 299.7 285.5 2167.2 2343.3 176.1
GOPE      13:168:64800 2.19 7.21 7.20 3.32 15.24 8.174 29.04 951.90 10.033 299.6 285.7 2166.8 2345.2 178.3
GOPE      13:168:68400 2.28 7.22 7.15 3.42 15.94 8.176 29.31 951.90 10.486 299.1 286.0 2166.8 2346.7 179.9
GOPE      13:168:72000 2.37 7.23 7.11 3.51 16.64 8.177 29.59 951.90 10.940 298.7 286.2 2166.8 2348.3 181.4
GOPE      13:168:75600 2.46 7.24 7.07 3.61 17.33 8.179 29.87 951.90 11.394 298.2 286.5 2166.8 2349.8 183.0
GOPE      13:168:79200 2.55 7.25 7.02 3.71 18.03 8.180 30.15 951.90 11.848 297.7 286.7 2166.8 2351.4 184.5
GOPE      13:168:82800 2.64 7.26 6.98 3.80 18.72 8.182 30.43 951.90 12.301 297.3 287.0 2166.8 2352.9 186.1
GOPE      13:169:00000 2.73 7.27 6.94 3.90 19.42 8.184 30.71 951.90 12.755 296.8 287.2 2166.8 2354.5 187.6
...
Z1MM      13:168:00000 3.02 7.12 6.87 3.86 18.78 8.106 28.07 912.71 12.261 294.8 284.1 2078.5 2253.5 175.0
Z1MM      13:168:03600 3.01 7.15 6.89 3.83 18.40 8.107 27.54 912.56 12.165 294.7 284.1 2078.2 2249.9 171.8
Z1MM      13:168:07200 3.00 7.18 6.91 3.80 18.02 8.108 27.01 912.41 12.069 294.5 284.1 2077.8 2246.3 168.5
Z1MM      13:168:10800 2.99 7.21 6.93 3.77 17.64 8.108 26.49 912.26 11.973 294.4 284.1 2077.5 2242.7 165.3
Z1MM      13:168:14400 2.98 7.24 6.95 3.74 17.26 8.109 25.96 912.11 11.877 294.3 284.1 2077.1 2239.2 162.0
Z1MM      13:168:18000 2.97 7.27 6.97 3.72 16.88 8.110 25.43 911.96 11.781 294.2 284.1 2076.8 2235.6 158.8
Z1MM      13:168:21600 2.96 7.30 6.98 3.69 16.49 8.111 24.91 911.81 11.685 294.0 284.1 2076.4 2232.0 155.5
Z1MM      13:168:25200 2.93 7.30 7.07 3.65 16.31 8.115 24.84 911.75 11.520 294.8 284.2 2076.3 2231.4 155.1
Z1MM      13:168:28800 2.90 7.28 7.18 3.62 16.20 8.120 24.94 911.71 11.347 295.8 284.3 2076.2 2231.8 155.6
Z1MM      13:168:32400 2.86 7.26 7.29 3.58 16.16 8.126 25.19 911.69 11.190 296.9 284.5 2076.2 2232.2 157.0
Z1MM      13:168:36000 2.82 7.24 7.42 3.53 16.17 8.131 25.57 911.68 11.070 298.1 284.7 2076.2 2235.4 159.3
Z1MM      13:168:39600 2.77 7.21 7.54 3.48 16.24 8.137 26.05 911.66 11.009 299.3 284.9 2076.1 2238.4 162.2
Z1MM      13:168:43200 2.71 7.19 7.65 3.42 16.34 8.143 26.63 911.63 11.031 300.2 285.0 2076.0 2241.9 165.8
Z1MM      13:168:46800 2.63 7.20 7.76 3.34 16.45 8.149 27.27 911.47 11.217 300.9 285.0 2075.7 2245.6 169.9
Z1MM      13:168:50400 2.55 7.21 7.87 3.24 16.60 8.155 28.02 911.29 11.488 301.5 285.1 2075.3 2249.9 174.7
Z1MM      13:168:54000 2.47 7.22 7.96 3.15 16.80 8.160 28.82 911.12 11.807 301.9 285.0 2074.9 2254.7 179.8
Z1MM      13:168:57600 2.39 7.22 8.02 3.06 17.01 8.164 29.64 911.01 12.138 302.1 285.0 2074.6 2259.8 185.1
Z1MM      13:168:61200 2.32 7.21 8.05 2.98 17.25 8.166 30.43 910.99 12.445 302.0 284.9 2074.6 2264.8 190.2
Z1MM      13:168:64800 2.27 7.19 8.04 2.92 17.50 8.165 31.15 911.09 12.692 301.7 284.7 2074.8 2269.7 194.9
Z1MM      13:168:68400 2.28 7.11 7.90 2.92 17.76 8.158 31.57 911.58 12.704 300.8 284.3 2075.9 2273.6 197.7
Z1MM      13:168:72000 2.29 7.04 7.75 2.93 18.01 8.150 32.00 912.08 12.716 299.9 283.9 2077.1 2277.6 200.5
Z1MM      13:168:75600 2.31 6.96 7.61 2.93 18.27 8.143 32.42 912.57 12.728 298.9 283.6 2078.2 2281.6 203.4
Z1MM      13:168:79200 2.32 6.88 7.47 2.93 18.53 8.135 32.85 913.07 12.740 298.0 283.2 2079.3 2285.5 206.2
Z1MM      13:168:82800 2.33 6.81 7.33 2.94 18.78 8.128 33.27 913.56 12.753 297.0 282.8 2080.4 2289.5 209.0
Z1MM      13:169:00000 2.34 6.73 7.19 2.94 19.04 8.120 33.70 914.05 12.765 296.1 282.5 2081.6 2293.4 211.8
-TROP/SOLUTION
%=ENDTRO

```


References

1. Askne J, Nordius H (1987), Estimation of tropospheric delay for microwaves from surface weather data, *Radio Science*, Vol. 22, No. 3, pp. 379-386, 1987.
2. Bevis M., Businger S., Chiswell S., Herring T. A, Anthes R. A., Rocken C., and Ware R. H. (1994), GPS Meteorology: mapping zenith wet delays onto precipitable water, *Journal of Applied Meteorology*, vol. 33, pp.379-386.
3. 'COST-Format' File Specification for Ground-based GNSS Delay and Water Vapour Data, http://egvap.dmi.dk/support/formats/egvap_cost_v22.pdf.
4. Davis J. L., Herring L. T. A, Shapiro I. I., Rogers A. E., and Elgered G. (1985), Geodesy by radio interferometry: Effects of atmospheric modelling errors on estimates of baseline length, *Radio Science*, vol. 20, pp. 1593-1607.
5. Dousa J, Elias M (2014), An improved model for calculating tropospheric wet delay, *Geophys. Res. Lett.*, 41, doi: 10.1002/2014GL060271.
6. Gendt, G. (1997): SINEX TRO—Solution (Software/technique) INdependent Exchange Format for combination of TROpospheric estimates Version 0.01, March 1, 1997:https://igsbc.jpl.nasa.gov/igsbc/data/format/sinex_tropo.txt
7. IERS convention 2010, Gérard Petit and Brian Luzum (eds.). (IERS Technical Note ; 36) Frankfurt am Main: Verlag des Bundesamts für Kartographie und Geodäsie, 2010. 179 pp., ISBN 3-89888-989-6.
8. Saastamoinen J. (1972), Atmospheric Correction for the Troposphere and Stratosphere in Radio Ranging of Satellites, in *The Use of Artificial Satellites for Geodesy*, vol. 15, S. W. Henriksen et al., Eds., Geophysics Monograph Series, A.G.U., Washington, D.C..
9. Smith WL (1966), Note on the relationship between total precipitable water and surface dew point, *J. Appl. Meteorol.*, 5, 726–727.
10. SINEX Format, <http://www.iers.org/iers/EN/Organization/AnalysisCoordinator/SinexFormat/sinex.html>.
11. The U.S. Standard Atmosphere (1976), Sponsorship of National Oceanic and Atmospheric Administration, National Aeronautics and Space Administration, U.S. Air Force, U.S. Government Printing Office, Washington, D. C.

Acknowledgment

This activity is carried out in the framework of WG3 'GNSS for Climate' of the COST Action ES1206 'Advanced Global Navigation Satellite Systems tropospheric products for monitoring severe weather events and climate (GNSS4SWEC)'. e-GEOS work was done under ASI contract 2015-050-R.O. GOP work was done under the framework of the national project (No. LD14102) by the Ministry of Education, Youth and Sports of the Czech Republic provided in support of the COST Action ES1206. D. Offiler (Met Office UK), H. Brenot (BIRA), M. Bender (DWD) are acknowledged for many useful suggestions.